

CUCM Upgrade to 8.6.1




Ryan Bennett

Note: All upgrade paths prior to 8.5(2) will REQUIRE the installation of a COP. The COP file will deliver functionality to (a) allow the upgrade path to be supported and (b) provide user experience enhancements. These capabilities are being delivered in a phased approach. The Phase I COP file will simply allow the upgrade path to be supported. Initially, upgrades from 8.5 will NOT require a COP file. The Phase II COP file delivers Refresh Upgrade User Experience Enhancements and was made available with AC2. Throughout AC3, we will deliver updates to the Phase II COP that will also deliver Refresh Upgrade User Experience Enhancements for the remaining upgrade paths.

- •Refresh Upgrade is initiated in the same manner as previous upgrades.
- •Refresh Upgrade (RU) is very different from the standard Upgrade (L2) from a user experience standpoint
- •User improvements, i.e. enhancements to the GUI and CLI, are delivered via the Refresh Upgrade COP, which is mandatory.
- •The following is what you will experience during a Refresh Upgrade
 - Initiate upgrade in typical manner
 - Phase 1: Data export
 - Phase 2: System reboots, installs rhel5, reboots, and install applications
 - Phase 3: Data import
 - The upgrade is complete and services will be started.
 - Note: Monitor the console for progress during the Refresh Upgrade.


Overview

Upgrade from 8.5.1 to 8.6.1 was done on a VMWare setup within the lab. Physical servers might work slightly different based on the model, so be sure to let your engineer know the exact model of the server first. Below is the information that you will see whenever you have the issue.




Overview

Error seen during the upgrade attempt:




Below is the error that you will see within the upgrade logs, but its not directly on the bottom, you will need to scroll up just a bit.

Below is the file that you will need to install prior to being able to complete the upgrade



ciscocm.refresh_upgrade_v1.0.cop.sgn is the full name of the file.

Continue stepping through the normal upgrade process



Tomcat restarts and then it takes about 5 – 10 minutes to get the Web Admin page back up and running.

Now go back and attempt the re-install, everything should work just fine.

After you complete the upgrade you will see the following:

admin:show version inactive

Active Master Version: 8.5.1.10000-26

Active Version Installed Software Options:

ciscocm.refresh_upgrade_v1.0.cop

admin:show version active

Inactive Master Version: 8.6.1.10000-12


Inactive Version Installed Software Options:


ciscocm.refresh upgrade v1.0.cop

Finally you will see the following, to confirm that you've upgraded the CUCM server successfully.



Other screens you might come across







Version Information

Current Version 8.5.1.12017-2 Upgrade Version 8.6.1.10000-24

UCSInstall_UCOS_8.6.1.10000-24.sgn.iso MD5 Hash Value c6:82:92:0c:c5:d4:b8:c3:b5:14:ed:d4:06:cd:fb:a7

Status

File

This is a Refresh Upgrade. Refresh Upgrades require an extended service outage and multiple reboots. Please refer to the Software Upgrades section of the Cisco Unified Communication Operating System Administration Guide for more



This server model requires a USB storage device in order to proceed with the upgrade. Please insert a USB storage device with at least 16GB of capacity. Note that any existing data on the USB device will be deleted. 1 This Refresh Upgrade will COMPLETELY REFORMAT YOUR SERVER. Reverting to your current version following the Refresh Upgrade will require a reinstall and restore. You must have a valid backup.



Welcome to the Platform Command Line Interface

admin:utils system upgrade initiate

Warning: Do not close this window without first canceling the upgrade.

Downloaded: UCSInstall_UCOS_8.6.1.10000-24.sgn.iso

File version: 8.6.1.10000-24

File checksum: c6:82:92:0c:c5:d4:b8:c3:b5:14:ed:d4:06:cd:fb:a7

Automatically switch versions if the upgrade is successful (yes/no): \blacksquare

Command Line Interface is starting up, please wait ...

Welcome to the Platform Command Line Interface

admin:utils system upgrade initiate

Warning: Do not close this window without first canceling the upgrade.

Downloaded: UCSInstall_UCOS_8.6.1.10000-24.sgn.iso

File version: 8,6,1,10000-24

File checksum: c6;82;92;0c;c5;d4;b8;c3;b5;14;ed;d4;06;cd;fb;a7

This is a Refresh Upgrade. Refresh Upgrades require an extended service outage and multiple reboots. Please refer to the Software Upgrades section of the Cisco Unified Communication Operating System
Administration Guide for more information.

Switch to new version if the upgrade is successful (yes/no): \blacksquare

Welcome to the Platform Command Line Interface

admin:utils system upgrade initiate

Warning: Do not close this window without first canceling the upgrade.

Downloaded: UCSInstall_UCOS_8.6.1.10000-24.sgn.iso

File version: 8.6.1.10000-24

File checksum: c6:82:92:0c:c5:d4:b8:c3:b5:14:ed:d4:06:cd:fb:a7

This is a Refresh Upgrade. Refresh Upgrades require an extended service outage and multiple reboots. Please refer to the Software Upgrades section of the Cisco Unified Communication Operating System Administration Guide for more information.

This server model requires a USB storage device in order to proceed with the upgrade. Please insert a USB storage device with at least 16GB of capacit y. Note that any existing data on the USB device will be deleted.

This Refresh Upgrade will COMPLETELY REFORMAT YOUR SERVER. Reverting to your current version following the Refresh Upgrade will require a reinstall and restore. You must have a valid backup.

Start Refresh Upgrade (yes/no): 🛮

2007 Cisco Systems, Inc. All rights reserved. Cisco Confidential

