

# Tidal Enterprise Scheduler: Enable AdapterHost Logging

Document ID: 112937

## Contents

**Introduction**

**Prerequisites**

Requirements

**Configure Adapter Logging**

**Related Information**

## Introduction

This document describes the process to enable additional logging on the AdapterHost and the Service Adapters.

## Prerequisites


### Requirements

Cisco Tidal Enterprise Scheduler 5.3.1 or later

## Configure Adapter Logging

In order to configure Adapter logging, complete these steps:

1. Go to **Administration > Connection**, and choose **Master Connection**.
2. From the Connection Definition (Edit Mode) window, adjust the **Host Environment Log** accordingly. This will configure the logging for both the AdapterHost and Service Adapters.



The screenshot shows a window titled "Connection Definition (Edit Mode)" with a subtitle "Master Connection". The window contains the following fields:

- Name:** Windows Master
- Machine Name:** Devtidal01
- Client-to-Master Port:** 6702
- Agent-to-Master Port:** 5591
- Host Environment Log:** Severe (selected from a dropdown menu)

Buttons for "OK" and "Cancel" are located in the top right corner. The window also features a tabbed interface with "Connection" and "Description" tabs.

3. The AdapterHost logs are stored in the master log directory. The service logs are stored in a subdirectory named **log**, located under each Service Adapter.

```
{MASTER_INSTALL_DIRECTORY/log}= AdapterHost

{MASTER_INSTALL_DIRECTORY/Services/{Adapter GUID}/log = Services Adapters

{MASTER_INSTALL_DIRECTORY/Services/{65C600D1-4316-41bd-8ED0-AB8E5F470838}/log
= Email Adapter

{MASTER_INSTALL_DIRECTORY/Services/{84E41389-A7FA-4834-9A63-3808C7B7D799}/log
= Horizon Adapter

{MASTER_INSTALL_DIRECTORY/Services/{CAFA6E81-E29F-4263-8E80-4928FFF416A2}/log
= MsSQL Adapter

{MASTER_INSTALL_DIRECTORY/Services/{DB7FB8C2-96AF-4790-9512-AFC8ECFE784D}/log
= OracleApps Adapter

{MASTER_INSTALL_DIRECTORY/Services/{3EC69AA3-C8C3-4a19-8F66-F36CFDDA5BB1}/log
= Oracle DB Adapter

{MASTER_INSTALL_DIRECTORY/Services/{B20EC120-2EB5-4d5f-8133-73FA37225667}/log
= Peoplesoft Adapter

{MASTER_INSTALL_DIRECTORY/Services/{51C57049-3215-44b7-ABE1-C012FF786010}/log
= SAP Adapter

{MASTER_INSTALL_DIRECTORY/Services/{A2277702-9011-49e9-991D-F2E7E7055C0E}/log
= TA Adapter

{MASTER_INSTALL_DIRECTORY/Services/{2C290052-71BA-47BC-85BB-D65E06459001}/log
= Webservice Adapter
```

## Related Information

- [Technical Support & Documentation – Cisco Systems](#)

---

[Contacts & Feedback](#) | [Help](#) | [Site Map](#)

© 2010 – 2011 Cisco Systems, Inc. All rights reserved. [Terms & Conditions](#) | [Privacy Statement](#) | [Cookie Policy](#) | [Trademarks of Cisco Systems, Inc.](#)

---

Updated: May 17, 2011

Document ID: 112937

---