

Manual NAT Policies (Section 1)

```
1 (inside) to (outside) source static any any destination static NETWORK_OBJ_10.8.40.0_24  
NETWORK_OBJ_10.8.40.0_24 no-proxy-arp route-lookup  
    translate_hits = 0, untranslate_hits = 0  
2 (inside) to (outside) source static any any destination static NET_10.1.0.0_24_Dev  
NET_10.1.0.0_24_Dev no-proxy-arp route-lookup  
    translate_hits = 0, untranslate_hits = 0
```

Auto NAT Policies (Section 2)

```
1 (inside) to (outside) source static HOST_10.1.1.8_tcp8081 interface service tcp 8081 8081  
    translate_hits = 0, untranslate_hits = 5  
2 (inside) to (outside) source static HOST_10.1.1.8_tcp9100 interface service tcp 9100 9100  
    translate_hits = 0, untranslate_hits = 0  
3 (inside) to (outside) source static HOST_10.8.32.10_tcp1701 interface service tcp 1701 1701  
    translate_hits = 0, untranslate_hits = 0  
4 (inside) to (outside) source static HOST_10.8.32.10_tcp1723 interface service tcp pptp pptp  
    translate_hits = 0, untranslate_hits = 0  
5 (inside) to (outside) source static HOST_10.8.32.10_udp4500 interface service udp 4500 4500  
    translate_hits = 0, untranslate_hits = 13  
6 (inside) to (outside) source static HOST_10.8.32.10_udp500 interface service udp isakmp isakmp  
    translate_hits = 0, untranslate_hits = 14  
7 (inside) to (outside) source static HOST_10.8.32.12 interface service tcp 3306 3306  
    translate_hits = 0, untranslate_hits = 834  
8 (inside) to (outside) source static HOST_10.8.32.12_tcp9001 interface service tcp 9001 9001  
    translate_hits = 0, untranslate_hits = 2  
9 (inside) to (outside) source static HOST_10.8.32.13 interface service tcp 6188 6188  
    translate_hits = 0, untranslate_hits = 0  
10 (inside) to (outside) source static HOST_10.8.32.13_tcp6180 interface service tcp 6180 6180  
    translate_hits = 0, untranslate_hits = 40  
11 (inside) to (outside) source static HOST_10.8.32.13_tcp6181 interface service tcp 6181 6181  
    translate_hits = 0, untranslate_hits = 25  
12 (inside) to (outside) source static HOST_10.8.32.13_tcp6182 interface service tcp 6182 6182  
    translate_hits = 0, untranslate_hits = 9  
13 (inside) to (outside) source static HOST_10.8.32.13_tcp6183 interface service tcp 6183 6183  
    translate_hits = 0, untranslate_hits = 0  
14 (inside) to (outside) source static HOST_10.8.32.13_tcp6185 interface service tcp 6185 6185  
    translate_hits = 0, untranslate_hits = 0  
15 (inside) to (outside) source static HOST_10.8.32.13_tcp6188 interface service tcp 6188 6188  
    translate_hits = 0, untranslate_hits = 0  
16 (inside) to (outside) source static HOST_10.8.38.81 interface service tcp 9101 9101  
    translate_hits = 0, untranslate_hits = 0  
17 (inside) to (outside) source static HOST_10.8.38.82 interface service tcp 9102 9102  
    translate_hits = 0, untranslate_hits = 0  
18 (inside) to (outside) source static HOST_10.8.38.83 interface service tcp 9103 9103  
    translate_hits = 0, untranslate_hits = 0  
19 (inside) to (outside) source static HOST_10.8.38.84 interface service tcp 9104 9104  
    translate_hits = 0, untranslate_hits = 0  
20 (inside) to (outside) source static HOST_10.8.38.85 interface service tcp 9105 9105  
    translate_hits = 0, untranslate_hits = 0  
21 (inside) to (outside) source static HOST_10.8.38.86 interface service tcp 9106 9106  
    translate_hits = 0, untranslate_hits = 0  
22 (inside) to (outside) source static HOST_172.16.1.2_udp5060 interface service udp sip sip  
    translate_hits = 0, untranslate_hits = 118
```

Manual NAT Policies (Section 3)

1 (inside) to (outside) source dynamic any interface
translate_hits = 366390, untranslate_hits = 107357

SCG-ASA#